

Tutoriel installation Audacity et encodeur MP3

Installation d'Audacity

Télécharger Audacity

The screenshot shows the Audacity website's download page for Windows. A yellow box highlights the button "Télécharger Audacity 1.2.6 pour Microsoft Windows". Below it, a dialog box titled "Ouverture de audacity-win-1.2.6.exe" is displayed, showing the file type as "Application" and the source as "http://ovh.dl.sourceforge.net". In the "Optional Downloads" section, the link "LAME MP3 encoder" is highlighted with an arrow. Another arrow points from the text below to this link.

Double-cliquer ensuite sur ce fichier pour lancer l'installation d'Audacity.

Installation de Lame Encoder

Pour exporter les fichiers wav en MP3, vous devez télécharger « Lame Encoder ».

Comme son nom l'indique Lame est un encodeur nécessaire (et gratuit) pour convertir les fichiers sous Audacity.


The screenshot shows the Audacity website's help page titled "How do I download and install the LAME MP3 encoder?". It explains that due to software patents, the free LAME encoder cannot be distributed by Audacity. It provides a list of instructions for Windows users: 1. Go to the LAME download page. 2. Under "For Audacity on Windows", left-click on the link "libmp3lame-win-3.97.zip" and save the zip folder. 3. Unzip the folder and save the file "lame_enc.dll". 4. The first time using "Export as MP3", Audacity will ask where "lame_enc.dll" is saved. 5. In case of difficulty, view instructions at the Audacity Wiki.

Choisir ce lien

For Audacity on Windows:
[libmp3lame-win-3.97.zip](#) (Issues? Some help [HERE](#))

Et après avoir dézippé ce fichier, enregistrer la dll nommée « lame_enc.dll », à un endroit quelconque sur votre disque dur.

Lorsque vous choisissez la première fois d'exporter un son wav par ex. en MP3



Audacity vous demande où se trouve le fichier « lame_enc.dll ».

Il suffit alors de lui indiquer le chemin.

Vous obtenez cette fenêtre qu'il n'est pas indispensable de renseigner

